



Motion Computing Software Release Note

Name	Motion Tablet Center
File Name	MCTabCtrSetup-1.2.6.2.zip
Release Date	February 10, 2015
This Version	1.2.6.2
Replaces Version	All previous versions
Intended Users	Motion CL920, R12, C5te, F5te, C5m and F5m users
Intended Product	Motion CL920, R12, C5te, F5te, C5m and F5m Tablet PCs ONLY
File Size	808 Kb
Supported Operating System	Windows 8.1 (64-bit)

Fixes in this Release

- Improved the error and status reporting for the Sensors page.
- Implemented other minor fixes and performance improvements.

What's New In This Release

- N/A

Known Issues and Limitations

- The Motion Tablet Center Power page may not dynamically show any changes made to the power settings if those settings are changed externally in Windows or BIOS.

Installation and Configuration Instructions

To install Motion Tablet Center 1.2.6.2, perform the following steps:

1. Uninstall any previous versions in Control Panel > Uninstall a program.
2. Download the update and save to the directory location of your choice.
3. Unzip the file to a location on your local drive.
4. Double-click the installer executable (.exe file) and follow the prompts.

Licensing

Refer to your applicable end-user licensing agreement for usage terms.