



## Motion Computing Software Release Note

Name	<b>Motion Barcode Reader 1.0.7.2</b>
File Name	<b>MCBarcode_Reader_Installer_1.0.7.2.zip</b>
Release Date	July 22, 2014
This Version	<b>1.0.7.2</b>
Replaces Version	All previous versions
Intended Users	<b>F5te/C5te and F5t/C5t users</b>
Intended Product	Motion F5te/C5te and F5t/C5t Tablet PCs ONLY
File Size	7 MB
Supported Operating System	Windows 8 (64-bit) and Windows 7 (32-bit/64-bit)

### Fixes in this Release

- Unable read special characters in Excel or within a Citrix environment.

### What's New in this Release

- Updated to Wedgelite version 1.0.0.7.

### Installation and Configuration Instructions

#### **To install the Barcode Reader 1.0.7.2 update, perform the following steps:**

1. Download the update and save to the directory location of your choice.
2. Unzip the file to a location on your local drive.
3. Uninstall any previous versions of "Motion Barcode Reader" software. Search "Program and Features" and select "Motion Barcode Reader" for uninstallation.
4. Double-click the installer (.exe file) and follow the prompts.
5. The update process may take some time. Do not manually power off the tablet during the update.

### Licensing

Refer to your applicable end-user licensing agreement for usage terms.