



Motion Computing Software Release Note

Name	OmniPass 8.01.18
File Name	Omnipass_32-bit_8.01.18.zip Omnipass_64-bit_8.01.18.zip
Release Date	July 15, 2014
This Version	8.01.18
Replaces Version	All previous 8.x.x and 7.x.x versions
Intended Users	Motion F5te and C5te users
Intended Product	Motion F5te and C5te Tablet PCs ONLY
File Size	106 MB
Supported Operating System	Windows 7 32-bit and 64-bit

Fixes in this Release

- System hang in S3/S4 when Internet Explorer 11 installed.

What's New In This Release

N/A

Known Issues and Limitations

- **This Omnipass version does not support direct upgrade from the older Omnipass 7.x.x and 8.0.x versions. The user has to uninstall the 7.x.x/8.0.x versions of Omnipass and the Authentec Fingerprint Software before installing this version. Upgrade from newer 8.1.x versions has no issue.**
- Windows 8 Metro Explorer password entering is not supported.

Installation and Configuration Instructions

To install this version update, perform the following steps:

1. Download this update to the directory location of your choice.
2. Unzip the file to a location on your local drive.
3. Back up your existing OmniPass profile (see OmniPass Help for details).
4. Double-click the installer (setup.exe) and follow the prompts.

Silent mode installation instructions:

Command line statement to install in silent mode – "Setup.exe /s"

Command line statement for silent uninstall –

32 bit: "\\Program Files\InstallShield Installation Information\{f4e57f49-84b4-4cf2- b0a1-8ca1752bdf7e}\Setup.exe" /s

64 bit: "\\Program Files (x86)\InstallShield Installation Information\{314FAD12-F785-4471-BCE8-AB506642B9A1}\Setup.exe" /s.

Licensing

Refer to your applicable end-user licensing agreement for usage terms.