



Motion Computing Software Release Note

Name	CL900 WebCam Firmware v3
File Name	CL900_WebCam_FW_v3.zip
Release Date	October 11, 2011
This Version	18-0001-0003
Replaces Version	All previous versions
Intended Users	Motion Computing CL900 users
Intended Product	Motion Computing CL900 Tablet PCs only
File Size	589 KB
Supported Operating System	Windows 7 (32-bit), all versions.

Fixes in this Release

- Resolve WebCam no preview issue with QuickNav.

Known Issues and Limitations

Occasionally other camera application software will interfere with the camera firmware update process. If you experience any issues updating the camera firmware please read the tech-note in the installer package for further information.

If the tablet serial number is 00345395 or less the firmware update tool will report no update required.

Installation and Configuration Instructions

To install the WebCam firmware update:

1. Download the WebCam firmware file and save it to a directory of your choice.
2. Unzip the file to a location on your local drive.
3. Double-click the installer (CL900_WebCam_FW_v3.exe) and follow the prompts.

Note: If the current firmware version displayed is 18-0001-0003 the WebCam is up to date and you do not need proceed with the update.

Licensing

Refer to your applicable end-user licensing agreement for usage terms.