
Release Notes - XT15 WEH 6.5 OS Image v8.10

Contents

[Description](#)

[Device Compatibility](#)

[Component Contents](#)

[Installation Requirements](#)

[Installation Instructions](#)

[Downloadable Software included in this Release](#)

Description

The following changes and fixes have been included in this CFE:

SPR NO	Synopsis
36217	Updated Battery Health Service to more reliably detect batteries that need to be serviced or replaced.

Device Compatibility

This software release has been approved for use with the following Zebra devices.

Device	Operating System
Omnii XT15	Windows Embedded Handheld 6.5 Professional
Omnii XT15f	Windows Embedded Handheld 6.5 Professional
Omnii XT15ni	Windows Embedded Handheld 6.5 Professional

Component Contents

N/A

Installation Requirements

MicroSD card 2GB or greater formatted as FAT32 OR USB Memory stick and Omnii docking cradle

Installation Instructions

To update the operating system software of the XT15, follow the procedure below:

1. The firmware can be upgraded using a USB Memory Stick or using a microSD Card.
2. The firmware file must be renamed 7545os.img
3. Copy the file containing the firmware upgrade and the Add-On cab file to the root directory of the USB memory stick or Micro SD card.
4. Install the USB memory stick into the docking cradle or install the Micro SD card into the Omnii in the Micro SD slot in the battery compartment.
5. Press and hold down the [Blue FN] key, the [SCAN] key and the [Power] key, simultaneously for a minimum of six seconds.
6. When the firmware update is complete, the device reboots to the main operating system.
7. Using File Explorer, locate and double click the Add-On cab file to begin installation.
8. When the Add-On cab update is complete, the device reboots to the main operating system.
9. Remove the MicroSD card from the device to prevent the device from performing the upgrade process again on the next cold boot, and then disconnect external power. The device is now ready to be used.

Downloadable Software Included in this Release

Filename	File Description
P745XW65CPCB081002.cab	Windows Embedded Handheld 6.5.3 Addon Cab - Simplified Chinese
P745XW65CPMI081002.img	Windows Embedded Handheld 6.5.3 OS Image - Simplified Chinese
P745XW65CTCB081002.cab	Windows Embedded Handheld 6.5.3 Addon Cab - Traditional Chinese
P745XW65CTMI081002.img	Windows Embedded Handheld 6.5.3 OS Image - Traditional Chinese
P745XW65DECB081002.cab	Windows Embedded Handheld 6.5.3 Addon Cab - German
P745XW65DEMI081002.img	Windows Embedded Handheld 6.5.3 OS Image - German
P745XW65ENCB081002.cab	Windows Embedded Handheld 6.5.3 Addon Cab - English

P745XW65ENMI081002.img	Windows Embedded Handheld 6.5.3 OS Image - English
P745XW65FRCB081002.cab	Windows Embedded Handheld 6.5.3 Addon Cab - French
P745XW65FRMI081002.img	Windows Embedded Handheld 6.5.3 OS Image - French
P745XW65ITCB081002.cab	Windows Embedded Handheld 6.5.3 Addon Cab - Italian
P745XW65ITMI081002.img	Windows Embedded Handheld 6.5.3 OS Image - Italian
P745XW65JPCB081002.cab	Windows Embedded Handheld 6.5.3 Addon Cab - Japanese
P745XW65JPMI081002.img	Windows Embedded Handheld 6.5.3 OS Image - Japanese
P745XW65KOCB081002.cab	Windows Embedded Handheld 6.5.3 Addon Cab - Korean
P745XW65KOMI081002.img	Windows Embedded Handheld 6.5.3 OS Image - Korean
P745XW65SICB081002.cab	Windows Embedded Handheld 6.5.3 Addon Cab - Spanish
P745XW65SIMI081002.img	Windows Embedded Handheld 6.5.3 OS Image - Spanish

Last Revised: 30/04/2019