
MC55E0 v02.57.00 WEHH 6.5 Classic Release Notes

[Introduction](#)

[Description](#)

[General Enhancements](#)

[Contents](#)

[Device Compatibility](#)

[Installation Requirements](#)

[Installation Instructions](#)

[Part Number and Release Date](#)

Introduction

With the MC55E0 Series, managers and task workers who spend their days inside your company walls have everything they need to take instant action, anywhere in your facility — indoors and outside. When it comes to meeting the needs of your workforce, the MC55E0 excels, offering the right level of features, the right level of rugged design and support for the most demanding business applications. The result? Workers in retail, hospitality, manufacturing, healthcare and government agencies can complete more tasks more accurately in less time, improving productivity and customer care. And with healthcare friendly colors, MC55E0-HC brings mobility to point-of-care applications, helping nurses and other caregivers eliminate errors at the patient bedside to improve the quality of care — and the patient experience

Description

Update Loader Image 02.57.00 contains the Software required to flash an MC55E0 device with Rev B software release.

- WEHH 6.5 Professional AKU 29377
- FPGA ver. 2.19
- SOTI MobiStage client version v12.4.0 (Build-1045)
- DDT Tool v1.3.9
- UNIFIED_SCANNER_VER_9
- Data Wedge v3.7.16

General Enhancements in 02.57.00:

- Fusion Software X_2.03.0.0.024R
Updated MC55E0 with latest regulatory rules

Contents

55X0w65HenUL025700.zip	OS update package (without clean application)
55X0w65HenUC025700.zip	OS update package (with Clean Application)
55X0w65HenAB025700.apf	AirBeam Package for OS update (without clean application)
55X0w65HenAC025700.apf	AirBeam Package for OS update (with Clean Application)

Device Compatibility

This software release has been approved for use with the following Zebra devices.

Device	Operating System
MC55E0	Microsoft WEHH 6.5 Professional

Installation Requirements

MC55E0 device must contain a released version of Microsoft WEHH 6.5 Professional

Installation Instructions

Update Loader Package:

Standard Update Procedure -Device is cleaned of all persistent storage data. use this to update your device to a newer version of the OS.

1. Download the Update Loader Package 55X0w65HenUL025700.zip \ 55X0w65HenUC025700.zip
2. Unzip 55X0w65HenUL025700.zip \ 55X0w65HenUC025700.zip package
 - a. Copy all files into either the \Temp folder on the device or at the root directory of a Storage Card.
 - b. If the contents are copied to SD card then place the SD card in the device to be upgraded.
 - c. Place the device to be upgrade on an A/C power.
 - d. Navigate to the SD Card or \Temp folder and invoke the program STARTUPDLDR.EXE.
 - e. The update will take about 5 minutes to complete. Please do not remove the device from A/C power during this time.
 - f. Once the download completes and the system reboots, the update is complete and the device is ready for use.

Airbeam Users:

Standard Update Procedure - This method erases all data in the Persistent storage of the device.

1. Download the Airbeam OSUpdate Package 55X0w65HenAB025700.apf \ 55X0w65HenAC025700.apf
2. Apply the Airbeam Update package
3. Once the download completes and the system reboots, the update is complete and the device is ready for use.

Downgrade to v01.57.04:

Standard Downgrade Procedure:

1. Download the Update Loader Package 55X0w65HenUL015704.zip
2. Unzip the package and copy all files into either the \Temp folder on the device or at the root directory of a Storage Card.
3. If the contents are copied to SD card then place the SD card in the device to be upgraded.
4. Place the device to be upgrade on an A/C power.
5. Navigate to the SD Card or \Temp folder and invoke the program STARTUPDLDR.EXE.
6. The update will take about 5 minutes to complete. Please do not remove the device from A/C power during this time.
7. Once the download completes and the system reboots, the update is complete and the device is ready for use.

Part Number and Release Date

55X0w65HenUL025700

55X0w65HenUC025700

55X0w65HenAB025700

55X0w65HenAC025700

January 17, 2018