
STAGENOW 3.0 INSTALLATION GUIDE



STAGENOW 3.0 INSTALLATION GUIDE

MN001501A11

Revision A

May 2018

No part of this publication may be reproduced or used in any form, or by any electrical or mechanical means, without permission in writing from Zebra. This includes electronic or mechanical means, such as photocopying, recording, or information storage and retrieval systems. The material in this manual is subject to change without notice.

The software is provided strictly on an "as is" basis. All software, including firmware, furnished to the user is on a licensed basis. Zebra grants to the user a non-transferable and non-exclusive license to use each software or firmware program delivered hereunder (licensed program). Except as noted below, such license may not be assigned, sublicensed, or otherwise transferred by the user without prior written consent of Zebra. No right to copy a licensed program in whole or in part is granted, except as permitted under copyright law. The user shall not modify, merge, or incorporate any form or portion of a licensed program with other program material, create a derivative work from a licensed program, or use a licensed program in a network without written permission from Zebra. The user agrees to maintain Zebra's copyright notice on the licensed programs delivered hereunder, and to include the same on any authorized copies it makes, in whole or in part. The user agrees not to decompile, disassemble, decode, or reverse engineer any licensed program delivered to the user or any portion thereof.

Zebra reserves the right to make changes to any software or product to improve reliability, function, or design.

Zebra does not assume any product liability arising out of, or in connection with, the application or use of any product, circuit, or application described herein.

No license is granted, either expressly or by implication, estoppel, or otherwise under any Zebra Technologies Corp. intellectual property rights. An implied license only exists for equipment, circuits, and subsystems contained in Zebra products.

Zebra and the Zebra head graphic are registered trademarks of ZIH Corp. The Symbol logo is a registered trademark of Symbol Technologies, Inc., a Zebra Technologies company.

Portions of this software are based in part on the work of the Independent JPEG Group.

Zebra Technologies Corporation Lincolnshire, IL U.S.A. http://www.zebra.com

Revision History

Change	Date	Description	
-01 Rev A	4/2015	Initial release	
-02 Rev A	8/2015	Update with StageNow 2.1 information	
-03 Rev A	12/2015	Update with StageNow 2.2 information	
-04 Rev A	4/2016	Update with StageNow 2.3 information, add Android Lollipop support	
-05 Rev A	8/2016	Update with StageNow 2.4 information	
-06 Rev A	10/2016	Update with StageNow 2.5 information	
-07 Rev A	1/2017	Update with StageNow 2.6 information	
-08 Rev A	5/2017	Update with StageNow 2.7 information	
-09 Rev A	11/2017	Update with StageNow 2.9 information Replace list of supported devices with link	
-10 Rev A	2/2018	Update with StageNow 2.10 information Update list of supported OS's	
-11 Rev A	5/2018	Update with StageNow 3.0 information Update list of supported OS's Add information regarding Chinese support	

Changes to the original guide are listed below:

TABLE OF CONTENTS

About This Guide

Introduction	vii
Chapter Descriptions	vii
Notational Conventions	
Related Documents	viii
Service Information	viii

Chapter 1: Getting Started

Introduction	1-1
StageNow Workstation Requirements	1-1
Device and MX Support	

Chapter 2: Software Installation

Introduction	2-1
Software Requirements	2-1
Installing the StageNow Workstation Tool	
Upgrading the StageNow Workstation Tool	
Upgrading to a Non-Released Version of the StageNow Workstation Tool	
Uninstalling StageNow	2-11
Log Files	
•	

Chapter 3: Client Configuration

Introduction	3-1
StageNow Client Installation	
Log Files	3-2

ABOUT THIS GUIDE

Introduction

The *StageNow 3.0 Installation Guide* provides instructions for installing, uninstalling, and upgrading the StageNow Staging Solution, and includes information on versions, compatibility, and system requirements.

Chapter Descriptions

Topics covered in this guide are as follows:

- *Chapter 1, Getting Started* describes the hardware and software requirements for setting up the StageNow Staging Solution.
- Chapter 2, Software Installation provides instructions for installing and uninstalling the StageNow Workstation Tool on a host computer/workstation, as well as information on prerequisite software.
- Chapter 3, Client Configuration describes the client device requirements for connecting StageNow to the device.

Notational Conventions

The following conventions are used in this document:

- Italics are used to highlight the following:
 - · Chapters and sections in this and related documents
 - · Dialog box, window and screen names
 - Drop-down list and list box names
 - Check box and radio button names
- Bold text is used to highlight the following:
 - Key names on a keypad
 - Button names on a screen.

- bullets (•) indicate:
 - Action items
 - Lists of alternatives
 - · Lists of required steps that are not necessarily sequential
- Sequential lists (e.g., those that describe step-by-step procedures) appear as numbered lists.

Related Documents

 StageNow User Help File, p/n MN-002672-xx - provides information on using the StageNow Staging Solution software.

For the latest version of this guide and all guides, go to: http://www.zebra.com/support.

Service Information

If you have a problem using the equipment, contact your facility's technical or systems support. If there is a problem with the equipment, they will contact the Customer Support Center at: http://www.zebra.com/support.

When contacting support, please have the following information available:

- Serial number of the unit
- Model number or product name
- Software type and version number

Zebra responds to calls by e-mail, telephone or fax within the time limits set forth in service agreements.

If your problem cannot be solved by support, you may need to return your equipment for servicing and will be given specific directions. Zebra is not responsible for any damages incurred during shipment if the approved shipping container is not used. Shipping the units improperly can possibly void the warranty.

If you purchased your business product from a Zebra business partner, please contact that business partner for support.

CHAPTER 1 GETTING STARTED

Introduction

This chapter includes the hardware and software requirements for setting up the StageNow Staging Solution.

StageNow Workstation Requirements

Following are the minimum requirements for the host computer to run the StageNow Workstation Tool:

- Operating system: Microsoft Windows 7 or 10 (64 bit) Professional English and Simplified Chinese
- Operating memory: 2 GB minimum
- Hard drive storage: 6 GB minimum (if .Net Framework is not already installed)
- Screen resolution: 1366 x 768 (16:9 ratio) recommended
- .Net Framework 4.5.
 .Net 4.5.1 is included in the StageNow installation wizard if required, and also available at http://www.microsoft.com
- StageNow Workstation Tool installer, available at http://www.zebra.com/support
- A PDF reader for supporting staging material, Adobe[®] Acrobat[®] Reader recommended.
- Java Runtime (JRE) to use Audio staging
- · Wireless network interface card to use the Wi-Fi Hotspot feature



NOTE For the Chinese version, download the appropriate Adobe Acrobat Reader which supports the corresponding Asian language to generate staging bar codes from a Staging profile.

Only MX versions 8.0 and above support staging devices with the Chinese locale using the StageNow tool.

Device and MX Support

StageNow supports all Zebra Nougat, Marshmallow, Lollipop, and KitKat Android devices that have MX installed. Each OS supports the following MX versions:

- Nougat: MX 7.0, 7.1, 7.2
- Marshmallow: MX 6.0 and higher
- Lollipop: MX 5.1 and higher
- KitKat: MX 4.4 and higher

For a list of the Zebra Android devices and versions that StageNow supports, go to: http://techdocs.zebra.com/stagenow/3-0/about/



NOTE The MX features that each device supports depend on the Android OS, OSX, and MX versions in the BSP. Select the applicable device version in the matrix located at http://techdocs.zebra.com/mx/compatibility/ to determine the supported features.

Zebra Nougat, Marshmallow, Lollipop, and KitKat devices that ship with the StageNow Client support all device configuration options that the StageNow Tool offers.

CHAPTER 2 SOFTWARE INSTALLATION

Introduction

This chapter describes how to install the StageNow Staging Solution software.

Software Requirements

The StageNow Workstation Tool requires and auto-installs Microsoft .NET Framework 4.5. The tool also includes the Staging Database and Staging Server.

Installing the StageNow Workstation Tool

The StageNow setup package is bundled with the required software.



NOTE Installing the StageNow Workstation Tool also installs the Staging Database and Staging Server. No separate installation is required for these components.

See *Upgrading the StageNow Workstation Tool on page 2-10* if you have an older version of the StageNow Workstation Tool installed on the host PC.

To install the Workstation Tool:

- 1. Download the setup package staging_solution.[Version Number].exe.
- 2. Double-click the setup package file.
- 3. If you do not already have .Net Framework 4.5, the installation process prompts you to install it.

	ageNow requires the following items to be installed on your computer. Click Install gin installing these requirements.
Status	Requirement
Installing	Microsoft .NET Framework 4.5.1 Full
istalling N	Aicrosoft .NET Framework 4.5.1 Full
stalling N	Aicrosoft .NET Framework 4.5.1 Full
istalling N	/licrosoft .NET Framework 4.5.1 Full

Figure 2-1 Installing .NET Framework

4. Select the appropriate language for installation.



Figure 2-2 Selecting a Language

5. Select **Install**. When Framework installation completes, a window appears stating that the wizard is preparing to install StageNow.

StageNow - InstallShield Wizard	d			
2 .	Preparing to Ins	tall		
	StageNow Setup is pre will guide you through wait.	eparing the InstallShield Wizard, wh the program setup process. Please	ich e	
	Extracting: ISSetup.dl			
			1	
		StageNow - InstallShield Wit	zard	
			正在>	准备安装
			Stagel 它将引	Wow 安装程序正在准备 InstallShield Wizard, 导您完成剩余的安装过程。请稍候。
			正在准	备安装
				取消

Figure 2-3 Initial Installation Window




Figure 2-4 Installation Wizard

6. Select Next to continue, or Cancel to cancel the installation.



NOTE If you select **Cancel**, select **Yes**, and then **Finish** to exit the installation process.



Figure 2-5 License Agreement Window

7. Select I accept the terms of the license agreement and select Next.




Figure 2-6 User Name Window

2 - 6 StageNow 3.0 Installation Guide

- 8. Enter a User Name and Company Name, and specify who can use the Workstation Tool.
- 9. Select Next.

StageNow - Installation Wizard		
	Please enter an Administrator Password. This password can not be re-set or changed. Al StageNow profiles and data will be associated to this Password. Password must be at least 4 characters in length.	
<u> </u>	Herenter Admin Password	83
	Stagehlow - InstallShield Wizard	
	OK 予約。 新育 StageNow 配 毛環を须至少为 4 个字	
	Shield Wizard	
InstallShield	<back 4-10="" cancel="" th="" 个字符<="" 信理员密码应该介于=""><th></th></back>	
	InstallSyldd	

Figure 2-7 Administrator Password Window (Error)

10. Enter, and then re-enter, a password (between 4 and 10 characters) for the administrator and select Next.

 \checkmark

NOTE All StageNow profiles and data are associated with this password.

If the two passwords entered do not match or are not the correct length, an error window appears. Select **OK** and enter the passwords properly.

StageNow - Installation Wizard			×		
Choose Destination Location Select folder where setup will inst	al files.				
	Setup will install StageNow in the following fold To install to this folder, click Next. To install to folder.		se and select another		
				到此文件夹,请单击"下一步"。要安装到其它文件夹 译其它文件夹。	,请单击"浏览",
	Destination Folder C: (Program Files (x86))(Symbol Technologies		Browse		
InstallStridd	< Back Next :		Cancel		
Instantisticio.	- Reer (Marry			的地文件夫—————	
			C:1	\Frogram Files \Symbol Technologies\	浏览 (8)
		InstallShield		<上-步(型) 下-步(型) >	取消

Figure 2-8 Destination Folder Window

11. Select Next to accept the default folder, or select Browse first to choose another installation folder.

StageNow - Installation Wizard		×		
Start Copying Files Review settings before copying	, files.			
	Setup has enough information to start copying the program files Current Settings: Zebra StageNowv2.10.1 Destination Directory: CiProgram Files (x86)(Symbol Technologies) Company Name: Zebra Technologies	*	序具有足够值息未开始复制程序文件 置: StageNew v3.0.1 注:	
InstallSheld	< Back Next>	Cancel	""C:VFrogram Files (x08)\Symbol Technologies\ 公司名称: Zebra Technologies	
	Install Sived		<上一步®) 下一步® >	取消

Figure 2-9 Review Settings Window

12. Select Next to accept the current settings, or select **Back** to make a change.

The wizard indicates that it is configuring the software for installation, then indicates that installation is almost complete.

StageNow - Installation Wizard			
StageNow - Installation Wize	ard		
StageNow installation is almost	st complete		
Û	Create StageNow shortout on the Desixtop Lounch StageNow Tool	■ 在桌面上创建 StageNow 快捷方式 ■ 順琦 StageNow 工具	
InstallShield	Next>	_	
	InstallShield	T-#03>	

Figure 2-10 Installation Almost Complete Window

 If desired, select checkboxes to create a shortcut on the desktop, and/or to launch the StageNow Workstation Tool, and select Next.




Figure 2-11 Download PDF Reader Window

14. Because staging material is presented in PDF files, the Wizard prompts you to download a PDF reader, or skip this if you already have a reader installed. Select the appropriate option and then select **Finish**.

NOTE If you chose to download Adobe Acrobat Reader, the reader installation page opens for quick download




Figure 2-12 StageNow Installation Complete Window

and installation.

Upgrading the StageNow Workstation Tool

If you have an older version of the StageNow Workstation Tool installed on the host PC, upgrade it.



NOTE Complete all incomplete profiles before upgrading the StageNow Workstation tool. Profiles that are incomplete after upgrading can exhibit unexpected behavior.

- 1. Download the setup package staging_solution.[Version Number].exe.
- Double-click the setup package file. InstallShield detects the existing version and displays the following message.




Figure 2-13 Upgrade Message

3. Select **Yes** to proceed with the upgrade, or **No** to retain the existing version and cancel the upgrade. If you select **Yes**, the next message asks whether to remove existing StageNow user data (Settings, Profiles, etc.).

Question	23	问题 23
Would you like to remove the current user data? (Non-current user data will stay intact and can be removed manually.)		"是否要删除当前用户数据?(非当前用户数据将保持不变并可以手动删除。)
<u>Y</u> es <u>N</u> o		Yes No

Figure 2-14 Remove Data Message

4. Select the desired option to continue the upgrade.

NOTE If you choose to retain existing data, the install process does not request an administrator password as it retains the existing password.

5. See Installing the StageNow Workstation Tool on page 2-2 for the remainder of the installation instructions.

Upgrading to a Non-Released Version of the StageNow Workstation Tool

If you are upgrading an older version of the StageNow Workstation Tool to a non-release version, InstallShield displays the following message:



Figure 2-15 Uninstall StageNow Message

Manually uninstall the existing version using **Control Panel > Programs > Programs and Features > Uninstall**, then run the setup package file again.

Uninstalling StageNow

To uninstall the StageNow Workstation Tool:

- 1. Select Control Panel > Programs > Programs and Features.
- 2. Double-click StageNow. The Installation Wizard opens.
- 3. Follow the steps in the Wizard to complete the uninstallation.

NOTE During uninstallation, the tool asks if you would like to remove your user and application (profile) data. Selecting **Yes** deletes all passwords, data, and profiles.




Figure 2-16 Remove Data Prompt

4. Select **Finish** to complete the uninstallation.

Log Files

StageNow Workstation Tool files are generated in the %userprofile%\AppData\Roaming\StageNow\AST\logs folder. Use these files for debugging and troubleshooting.

CHAPTER 3 CLIENT CONFIGURATION

Introduction

This chapter describes the client device requirements for connecting StageNow to the device, and lists the Android devices supported.

StageNow Client Installation

StageNow supports all Nougat, Marshmallow, Lollipop, and KitKat Android devices from Zebra. Nougat, Marshmallow, Lollipop, and KitKat devices that ship with the StageNow Client installed support all device configuration options that the StageNow Tool offers.

Log Files

Use device log files for debugging and troubleshooting. To review the log to determine the cause of an error, select **Yes** from the staging failure screen, or from the StageNow Client menu, select **Last Staging Error**.






Figure 3-1 Viewing Logs

You can also view logs via the ADB Logcat.



Zebra Technologies Corporation Lincolnshire, IL U.S.A. http://www.zebra.com

©2018 ZIH Corp and/or its affiliates. All rights reserved. ZEBRA and the stylized Zebra head are trademarks of ZIH Corp, registered in many jurisdictions worldwide. All other trademarks are the property of their respective owners.