

MT20X0 CANNOT ADJUST LCD BACKLIGHT BRIGHTNESS HOTFIX, VERSION 0.0.0.8

DESCRIPTION

This hotfix fixes the issue that the MT20x0 can not adjust LCD backlight brightness.

DEVICE COMPATIBILITY

MT2070

MT2090

RELEASE NOTES

VERSION V.0.0.0.8

This hotfix fixes the issue that the MT20x0 can not adjust the LCD backlight brightness.

COMPONENTS

The installed files should be in the following folder on the scanner.

Component	Location
backlightdrv.dll	\Platform\
backlightdrv.cpy	\Platform\

INSTALLATION

The following is the procedure to apply the Hotfix. It is assumed that the ActiveSync installed on the PC.

- 1) ActiveSync the scanner to a PC;
- 2) Open up the "Platform" folder on the device using "Explore" on ActiveSync;
- 3) Copy the **backlightdrv.dll** and **backlightdrv.cpy** files to "\Platform" folder;
- 4) Cold boot the scanner (by press and hold scan trigger and '2' key. Wait for screen going black the 2nd time and release the trigger and key. Or, just remove the battery and reinsert it to cold boot.)

The scanner should boot up with the Hotfix applied.