

WORKABOUT PRO 4 OPERATING SYSTEM BSP 2.0 - HOTFIX CFE 2.4 RELEASE NOTES

INTRODUCTION

The Workabout Pro 4 is a modular, industrial hand held computer. Microsoft Windows CE Professional 6 is one of the two OS options for this device.

DESCRIPTION

Improvements in the OS release:

- Update OS branding.

- Integrate ETSI EN 300 328 v1.8.1 compliance improvements from '7528 Release 2.3 OS Patch v1.1'.

- Improve functionality on devices with both camera and imager.

- Improve suspend/resume and warm reset reliability.

- Improve browsing.

CONTENTS

7528 WinCE 6 OS Image v2.4

DEVICE COMPATIBILITY

This software release has been approved for use with the following Symbol devices.

Device	Operating System
Workabout Pro 4 (7528)	Windows CE 6.0 Professional



INSTALLATION REQUIREMENTS

If previously installed, uninstall '7528 Release 2.3 OS Patch v1.1'.

INSTALLATION INSTRUCTIONS

To uninstall 7528 Release 2.3 OS Patch v1.1, follow the procedure below:

- 1. Delete contents of \Application\tiinit folder.
- 2. Clean start device or update operating system software.

To update the operating system software of the WAP 4, follow the procedure below:

- 1. If previously installed, uninstall '7528 Release 2.3 OS Patch v1.1' (Instructions above).
- 2. The firmware can be upgraded using a USB Memory Stick or using a microSD Card.
- 3. The firmware file must be renamed 7528os.img
- 4. Copy the file containing the firmware upgrade to the root directory of the USB memory stick or Micro SD card
- 5. Install the USB memory stick into the docking cradle or install the Micro SD card into the WAP 4 in the Micro SD slot in the battery compartment
- 6. Press and hold down the [Blue FN] key, the [SCAN] key and the [Power] key, simultaneously for a minimum of six seconds.
- 7. When the update is complete, the device reboots to the main operating system.
- 8. Remove the MicroSD card from the device to prevent the device from performing the upgrade process again on the next cold boot, and then disconnect external power. The device is now ready to be used.
- 9. Install add-on cab file.

PART NUMBER AND RELEASE DATE

P728XC60CTMI020400 P728XC60CPMI020400 P728XC60EFMI020400 P728XC60JPMI020400 P728XC60KOMI020400



April 16, 2015